




# SPM Software Installation Instructions

In the Software version window, the user can see the current software version loaded on the power meter and update the meter with a future software update.

The latest software version can be downloaded from the Setra Power Meter product page:  
<https://www.setra.com/product/power-meters/setra-power-meter#downloads>

To update software version:

1. Download new software version from link above & save to preferred location
  2. Log into the web portal
  3. Click System page from the sidebar
  4. In the software version window, Click UPDATE button
- 
5. Choose new file from saved location, unit will take a few minutes to load new software and reboot
  6. Repeat step 5; when upgrading from 2.8.9 to 2.8.10, the software must be uploaded twice to ensure proper loading. Future version will only need to be loaded once.



Note: All trend data and configuration files should be saved prior to updating software  
(see manual for details)



**Setra Systems, Inc.**  
159 Swanson Road Boxborough, MA 01719  
800.257.3872 • [www.setra.com](http://www.setra.com)