

SPM Software Release Notes

Version 2.8.15

Bugs

- Fixed – Alarming, maximum number of alarms set at 100, warning message during alarm configuration step for when over and under alarms are created using the same setpoint
- Fixed – BACnet
 - Alarming improvements to increase uptime of system
 - Restart when new IP signal is added
 - Enhance communication robustness
 - Improve IPv6 tagging for separate addresses
 - Improved communication when communicating across subnets
- Fixed – Modbus
 - Improved communication when communicating across subnets
 - Allow reconnection in the Modbus subsystem
 - Allow slave identifiers in the full range of 1-247 in Modbus-control
- Fixed - .Enhanced protection against json file protection
- Fixed – Portal
 - Enhanced robustness of portal stability
 - MAC address check added between kernel and portal
- General uptime improvements for reliability in the field
- Added operating system log download via portal for troubleshooting
- Fixed – Total Energy Usage BACnet object

Have a question?



Talk to a Setra representative today about your project needs.



800.257.3872



www.setra.com